

--- bidmaxCalc Intallation Notes ---

Updated November 16, 2009

October 21, 2009

Running OS Platforms:

=====

bidmaxCalc is designed to run on the following OS platforms:

Windows Vista (Home, Premium, Ultimate), Windows XP, Mac OS Darwin (Tiger), Debian Linux.

These are the platforms bidmaxCalc has been tested for:

- Mac OS
- freeBSD Unix
- Unbuntu
- Debian Linux
- Sun Solaris.

Computer Hardware Requirements

=====

A minimum of 2GB of RAM (Windows Vista recommends at least 3GB of RAM) and 2GB of Free storage. Typical machine currently available on the market are dual core with 4GB or RAM and 350MB of storage which is more than enough.

Software Requirements

=====

bidmaxCalc runs on Java Virtual machine normally installed on all platforms. bidmaxCalc requires JRE (Java Run-time Edition) 1.6 and higher. If your machine is not equipped with this version or you need to install java this how to download and install the latest version go the following website: <http://java.sun.com>

Authorization

=====

Unless you are using the 30-day Free Trial Version bidmaxCalc will not run without a proper Access Key which is delivered once you have purchased bidmaxCalc.

bidmaxCalc software size

=====

bidmaxCalc is very light, its download size is about 0.25Mb and its footprint size is less than 100kb. It will download in less than a second if using a fast Internet connection. It could be easily used as an email attachment.

Download and Installation - Windows Vista

=====

bidmaxCalc comes in a variety of install packages the most common is bidmaxCalc.zip or bidmaxCalc.exe as a self extract file. You will need to unzip first bidmaxCalc in any designated folder say C:\bidmaxCalc. For those who are savvy you may create an environment variable called BIDMAXCALC_HOME pointing to C:\bidmaxCalc. To do so go to the control pannel under:

Control Panel > System and Maintenance > System

and click on Advance system settings. There click on Environment Variables and create a new entry called BIDMAXCALC_HOME save and open for edit the PATH environment variable append %BIDMAXCALC_HOME% and save.

Creating BIDMAXCALC_HOME environment variable is not necessary.

Running bidmaxCalc
=====

To run bidmaxCalc just double click on the file bidmaxCalc.jar or execute the following command also contained in file: bidmaxCalc.bat (Windows) or bidmaxCalc.sh (Mac, Linux, Unix)